HAZMAP 3.0

Computer Code and Related Documentation

Arnau Folch, Antonio Costa and Giovanni Macedonio

Istituto Nazionale di Geofisica e Vulcanologia
Sezione "Osservatorio Vesuviano"
Via Diocleziano 326 -80124 Napoli, Italy

June 2007

Contents

1 Introduction **3**

2 Program setup **4**
2.1 Installation 4
2.2 Folder structure 4
2.3 Program run 4

3 The HAZMAP 3.0 input files **6**
3.1 The control file `FileInp` 6
3.1.1 BLOCK TIME_UTC 6
3.1.2 BLOCK GRID 6
3.1.3 BLOCK HAZMAP 6
3.2 The source file `FileSrc` 7
3.3 The granulometry file `FileGrn` 7
3.4 The meteo data file `FileMet` 8

4 The HAZMAP 3.0 output files **9**
4.1 The list file `FileLst` 9
4.2 The results file `FileRes` 9

5 The utility programs **9**
5.1 The program SETGRN 9
5.1.1 Program execution 9
5.1.2 The GRANULOMETRY block 10
5.2 The program SETSRC 10
5.2.1 Program execution 11
5.2.2 The SOURCE block 11
5.3 The program MODELPOSTP 12
5.3.1 Program execution 12
5.3.2 The POSTPROCESS_MODELS block 12

6 References **14**

1 Introduction

HAZMAP 3.0 is a FORTRAN90 code for the solution of the equation of diffusion, transport and sedimentation of small particles, in order to model the dispersion of ash generated by a convective column. Under the approximations of a constant horizontally uniform wind field and negligible vertical advection and diffusion, this equation reduces to:

$$\frac{\partial C_j}{\partial t} + u_x \frac{\partial C_j}{\partial x} + u_y \frac{\partial C_j}{\partial y} - \frac{\partial (V_j C_j)}{\partial z} = K \left(\frac{\partial^2 C_j}{\partial x^2} + \frac{\partial^2 C_j}{\partial y^2} \right) + S_j \tag{1}$$

where C_j is the concentration of the particle velocity-class j having a settling velocity V_j, $\mathbf{u} = (u_x, u_y)$ is the wind velocity, K is the (constant) horizontal turbulent diffusion coefficient, and S_j is the source term. Since the above expression is linear in mass, an instantaneous release of the total mass from the eruption column can be assumed if wind and diffusion parameters do not change significantly with time and only the final deposit is needed. This quasi-steady approach is assumed to hold during each simulation time interval. Considering these approximations, the above equation has a semi-analytical solution as described in (Macedonio et al., 2005). The computational domain is split into thin horizontal layers that fall to the ground together with the particles originally contained in a given initial vertical interval $[z_i, z_{i+1}]$ at time $t = 0$. An analytical solution is then found for each layer. Since the whole treatment is done separately for each class of particles and no vertical diffusion and wind advection takes place, all particles falling from the same initial height remain at all times at the same altitude. While the centre of each cloud is translated by wind, the cloud spreads horizontally due to diffusion and settles by gravity until it reaches the ground where it forms the deposit. The model outputs therefore accumulations on the ground for each granulometric class. For further details see (Macedonio et al., 2005) and (Pfeiffer et al., 2005).
Settling velocity fits contemplated by HAZMAP 3.0 include:

- `ARASTOOPOUR` (Arastoopour et al., 1982)

$$V = \sqrt{\frac{4gd\rho_p}{3C_d\rho_a}} \tag{2}$$

$$C_d = \begin{cases} \dfrac{24}{Re(1+15Re^{0.687})} & Re \le 10^3 \\ 0.44 & Re > 10^3 \end{cases} \tag{3}$$

  where ρ_a and ρ_p stand, respectivelly, for the air and particle densities, d is the particle diameter, Re is the Reynolds number and C_d is a drag coefficient.

- `GANSER` (Ganser , 1993)

$$V = \sqrt{\frac{4gd\rho_p}{3C_d\rho_a}} \tag{4}$$

$$\begin{cases} C_d = \dfrac{24}{ReK_1}\left\{1 + 0.1118\left[Re\,(K_1K_2)\right]^{0.6567}\right\} + \dfrac{0.4305K_2}{1 + \dfrac{0.4305}{ReK_1K_2}} \\ K_1 = 3/(1+2\psi^{-0.5}) \\ K_2 = 10^{1.84148(-\mathrm{Log}\psi)^{0.5743}} \end{cases} \tag{5}$$

  where ψ is the particle sphericity (=1 for spherical particles).

- `WILSON` (Wilson and Wang , 1979)

$$V = \sqrt{\frac{4gd\rho_p}{3C_d\rho_a}} \tag{6}$$

$$C_d = \begin{cases} \dfrac{24}{Re}\phi^{-0.828} + 2\sqrt{1.07-\phi} & Re \le 10^2 \\ \dfrac{1 - C_d(Re=100)}{900}(Re - 1000) + 1 & 10^2 \le Re \le 10^3 \\ 1 & Re \ge 10^3 \end{cases} \tag{7}$$

  where ϕ is the aspect ratio $(b+c)/2a$ (a, b, c ellipsoidal semi-axes).

- `DELLINO` (Dellino et al., 2005).

$$V = \frac{1.2065\mu}{d\rho_a}\left(d^3(\rho_p - \rho_a)\rho_a\Psi^{1.6}/\mu^2\right)^{0.5206} \quad (8)$$

where μ is the air viscosity and Ψ is the shape factor (sphericity to circularity ratio).

2 Program setup

2.1 Installation

- On a Windows OS download and decompress the file `hazmap-3.0.tar.gz` on your selected directory. The `hazmap-3.0.tar` file already contains Windows executables for HAZMAP 3.0 and other utility programs so that it is not strictly necessary to have a FORTRAN90 compiler. The untaring of `hazmap-3.0.tar` will create the folders described in the Table 1.

- On a Unix/Linux/Mac X operating system:

  1. Decompress and then untar the file `hazmap-3.0.tar` issuing the command "`tar xvf hazmap-3.0.tar`". This will generate directory `Hazmap-3.0` (see Table 1).
  2. Compile the program HAZMAP 3.0 . Enter the directory `Hazmap-3.0/Sources`, then issue the command "`make`" to produce the executable Hazmap.exe. You can edit the Makefile to select your favourite compiler. After compilation you may issue the command "`make clean`" to remove unneeded files. If you are not going to run on a Windows platform you can also delete the executable Hazmap.win.exe.
  3. Compile the (optional) utility program SETGRN . Enter the directory `Hazmap-3.0/Utilities/SetGrn/Sources`, then issue the command "`make`" to produce the executable SerGrn.exe. You can edit the Makefile to select your favourite compiler. After compilation you may issue the command "`make clean`" to remove unneeded files. If you are not going to run on a Windows platform you can also delete the executable SetGrn.win.exe.
  4. Compile the (optional) utility program SETSRC . Enter the directory `Hazmap-3.0/Utilities/SetSrc/Sources`, then issue the command "`make`" to produce the executable SerSrc.exe. You can edit the Makefile to select your favourite compiler. After compilation you may issue the command "`make clean`" to remove unneeded files. If you are not going to run on a Windows platform you can also delete the executable SetSrc.win.exe.
  5. Compile the (optional) utility program MODELPOSTP . Enter the directory `Hazmap-3.0/Utilities/ModelPostp/Sources`, then issue the command "`make`" to produce the executable ModelPostp.exe. You can edit the Makefile to select your favourite compiler. After compilation you may issue the command "`make clean`" to remove unneeded files. If you are not going to run on a Windows platform you can also delete the executable ModelPostp.win.exe.

2.2 Folder structure

Table 1 shows the folder structure. The directory `Hazmap-3.0/Sources` contains the HAZMAP 3.0 source files, the directory `Hazmap-3.0/Utilities` contains the programs SETGRN , SETSRC and MODELPOSTP and, finally, the directory `Hazmap-3.0/Runs` contains the runs, one within each own folder. An example run named "Example" is provided with the installation.

2.3 Program run

HAZMAP 3.0 can be launched typing
"`Hazmap.exe FileInp FileSrc FileGrn FileMet FileLst FileRes`" (on a Unix/Linux/Mac X OS)
or
"`Hazmap.win.exe FileInp FileSrc FileGrn FileMet FileLst FileRes`" (on a Windows OS), where

- `FileInp`: Name (including path) of the control input file (see section 3.1).

Table 1: Default directory structure.

hazmap-3.0	Sources	
	Utilities	SetGrn
		SetSrc
		ModelPostp
	Runs	Example
		....

- `FileSrc`: Name (including path) of the source input file (see section 3.2).
- `FileGrn`: Name (including path) of the granulometry input file (see section 3.3).
- `FileMet`: Name (including path) of the meteo data input file (see section 3.4).
- `FileLst`: Name (including path) of the output list file (see section 4.1).
- `FileInp`: Name (including path) of the HAZMAP 3.0 results file (see section 4.2).

Note that filenames (and locations) are passed as a program call argument. It is highly recomended to launch HAZMAP 3.0 through the script files included in the distribution.

- On a Windows OS enter the folder `Hazmap-3.0`, edit the script `Script-Hazmap-Win.bat` to change the "problemname" variable and launch the script.
- On a Mac X/Unix/Linux OS enter the folder `Hazmap-3.0`, edit the script `Script-Hazmap-Unix` to change the "problemname" variable and launch the script.

NOTE: To create a new run you can simply create a new folder, copy the control input file of the example (Example.inp) and modifiy the script line which defines the "problemname" variable.

3 The HAZMAP 3.0 input files

3.1 The control file `FileInp`

The HAZMAP 3.0 control file is passed to the program as a call argument. This file is made up with a set of blocks that define all the computational and physical parameters needed by the dispersion model (Table 2 shows an example of control file). Parameters within a block are listed one per record, in arbitrary order, and can optionally be followed by one or more blank spaces and a comment. A detailed description of each record is given below. Real numbers can be expressed following the FORTRAN notation (*e.g.*, $12e7 = 12 \times 10^7$).

3.1.1 BLOCK TIME_UTC

This block of data defines variables related to time.

- `YEAR`: Current year.
- `MONTH`: Current month (1-12).
- `DAY`: Current day (1-31).
- `RUN_START_(HOURS_AFTER_00)`: Run start hour (after 0000UTC).
- `RUN_END_(HOURS_AFTER_00)`: Run end hour (after 0000UTC).

3.1.2 BLOCK GRID

This block of data defines variables related to the grid at ground.

- `X_ORIGIN_(UTM_M)`: x-coordinate of the grid bottom left corner (UTM coordinates in m).
- `Y_ORIGIN_(UTM_M)`: y-coordinate of the grid bottom left corner (UTM coordinates in m).
- `CELL_SIZE_(KM)`: Grid spacing (in km).
- `NX`: Number of grid cells along the x-direction.
- `NY`: Number of grid cells along the y-direction.

3.1.3 BLOCK HAZMAP

This block of data defines the rest of variables needed by the program.

- `ZLAYER_(M)`: Heights (in m) of the z-layers in terrain following coordinates, *i.e.* above the vent. It is not necessary to specify the number of vertical layers since it is automatically calculated by the program.
- `ZVENT_(M)`: Height (in m a.s.l.) of the vent.
- `TERMINAL_VELOCITY_MODEL`: Type of terminal settling velocity model. Possibilities are `ARASTOOPOUR` (Arastoopour et al., 1982), `GANSER` (Ganser , 1993), `WILSON` (Wilson and Wang , 1979) and `DELLINO` (Dellino et al., 2005).
- `TERMINAL_VELOCITY_MODEL_FACTOR`: Model dependent factor. For `ARASTOOPOUR` it is not used. For `GANSER` it is the sphericity ψ (see 5). For `WILSON` it is the aspect ratio ϕ (see 7). Finally, for `DELLINO` it is the shape factor Ψ (see 8).
- `HORIZONTAL_DIFFUSION_COEFFICIENT_(M2/S)`: Value of the diffusion coefficient K (in m^2/s).
- `POSTPROCESS_TIME_INTERVAL_(HOURS)`: Time interval to output results (in h).

Table 2: Sample of the input control file `FileInp`.

```
TIME_UTC
YEAR = 2007
MONTH = 03
DAY = 01
RUN_START_(HOURS_AFTER_00) = 0.
RUN_END_(HOURS_AFTER_00) = 3.

GRID
X_ORIGIN_(UTM_M) = 450000.
Y_ORIGIN_(UTM_M) = 4125000.
CELL_SIZE_(KM) = 2.0
NX = 51
NY = 51

HAZMAP
Z_LAYER_(M) = 0 10 50 100 200 400 600 800 1000 1500 2000 2500 3000 3500 4000 4500 5000 5500 6000
Z_VENT_(M) = 3030.
TERMINAL_VELOCITY_MODEL = Ganser
TERMINAL_VELOCITY_MODEL_FACTOR = 1.0
HORIZONTAL_DIFFUSION_COEFFICIENT_(M2/S) = 1000.
POSTPROCESS_TIME_INTERVAL_(HOURS) = 3.
```

3.2 The source file `FileSrc`

The HAZMAP 3.0 source file is an ASCII file containing the definition of the source term. The source is defined at time intervals during which source values are kept constant. The number, position and values (*i.e.* Mass Flow Rate) of the source points can, however, vary from one time slice to another. There is no restriction on the number and duration of the time intervals. It allows, in practise, to discretize any type of source term. This file can be created by the utility program SETSRC . The file format is described in Table 3 and the meaning of the used symbols is the following:

- `itime1`: Starting time (in sec after 00UTC) of the time slice.
- `itime2`: End time (in sec after 00UTC) of the time slice.
- `nsrc`: Number of source points (can vary from one interval to another).
- `nc`: Number of granulometric classes.
- `MFR`: Mass flow rate (in kg/s).
- `x`: x-coordinate of the source isrc (UTM coordinates in m).
- `y`: y-coordinate of the source isrc (UTM coordinates in m).
- `z`: z-coordinate of the source isrc (terrain following coordinates in m, *i.e.* above the vent).
- `src`: Mass flow rate (in kg/s) of each granulometric class for this point source. It must be verified that $\sum\sum src(isrc, ic) = MFR$.

3.3 The granulometry file `FileGrn`

The HAZMAP 3.0 granulometry file is an ASCII file containing particle densities and granulometric distribution. This file can be created by the utility program SETGRN . The file format is described in Table 4 and the meaning of the used symbols is the following:

Table 3: Format of the source file `FileSrc`. Repeat thes block for each time slice

.

itime1 itime2
nsrc nc
MFR
x y z src(1,1) ... src(1,nc)
...
x y z src(nsrc,1) ... src(nsrc,nc)

Table 4: Format of the granulometry file `FileGrn`.

nc
diam(1) rho(1) fc(1)
...
diam(nc) rho(nc) fc(nc)

- `nc`: Number of granulometric classes.
- `diam`: Class diameter (in mm).
- `rho`: Class density (in kg/m^3).
- `fc`: Class mass fraction (0-1). If must verify that $\sum$ fc $= 1$.

3.4 The meteo data file `FileMet`

The HAZMAP 3.0 meteo data file is an ASCII file containing wind velocities and air temperatures at different heights and for each time slice. The vertical layers at which meteo data is provided can be different in number and location from the HAZAMP z-layers defined in the record Z_LAYER_(M) of the control input file. The program automatically interpolates data from the formers to the latters. The file format is described in Table 5 and the meaning of the used symbols is the following:

- `itime1`: Starting time (in sec after 00UTC) of the time slice.
- `itime2`: End time (in sec after 00UTC) of the time slice.
- `nz`: Number of z-layers at which meteo data is provided.
- `z`: z-coordinate of the layer (terrain following coordinates in m).
- `ux`: x-component of the wind velocity (in m/s).
- `uy`: y-component of the wind velocity (in m/s).
- `T`: Temperature (in ^oC).

Table 5: Format of the meteo file `FileMet`. Repeat this block for each time slice.

itime1 itime2
nz
z(1) ux(1) uy(1) T(1)
...
z(nz) ux(nz) uy(nz) T(nz)

4 The HAZMAP 3.0 output files

4.1 The list file `FileLst`

This file contains information concerning the run (summary of input data, run time error messages, CPU time, *etc.*).

4.2 The results file `FileRes`

This is a binary file with the results from a HAZMAP 3.0 run. Results are output at the nodes of a regular 2d grid. This file must be processed by the MODELPOSTP utility to produce "human readeable" files (normally in GRD format).

5 The utility programs

5.1 The program SETGRN

The granulometric distribution is defined in the granulometry file (see section 3.3). The program SETGRN is an utility that reads the GRANULOMETRY block from the control input file and generates the granulometry file assuming that the mass fraction of particles follows either a linear or Gaussian distribution in Φ and that the density of particles varies linearly with Φ. Note that other granulometric distributions different from a linear/Gaussian can also be considered. However, in this case, the HAZMAP 3.0 granulometry file can not be generated by SETGRN but must be supplied directly by the user.

5.1.1 Program execution

To run SETGRN (see section 2.1 for installation details) simply type
"`SetGrn.exe FileLog FileInp FileGrn`" (on a Unix/Linux/Mac X OS) or
"`SetGrn.win.exe FileLog FileInp FileGrn`" (on a Windows OS) where

- `FileLog`: Name (including path) of the SETGRN output log file.
- `FileInp`: Name (including path) of the control input file that contains the GRANULOMETRY block. Normally this file coincides with the HAZMAP 3.0 input file.
- `FileGrn`: Name (including path) of the granulometry file. This is the output from SETGRN that is used later by HAZMAP 3.0 as input.

Note that filenames are passed as a program call argument. It is highly recomended to launch SETGRN through the script files included in the distribution.

- On a Windows OS go to the folder `Hazmap-3.0/Utilities/SetGrn`, edit the script `Script-SetGrn-Windows` to change the "problemname" variable and launch the script.
- On a Mac X/Unix/Linux OS enter the folder `Hazmap-3.0/Utilities/SetGrn`, edit the script `Script-SetGrn-Unix` to change the "problemname" variable and launch the script.

Table 6: Sample of the SETGRN input file. Normally this block is appended at the end of the HAZMAP 3.0 input file.

```
GRANULOMETRY
NUMBER_OF_CLASSES = 12
DISTRIBUTION = GAUSSIAN
FI_MIN = 0
FI_MAX = 5
GAUSSIAN_DISTRIBUTION
FI_MEAN = 2.5
FI_DISP = 1.5
LINEAR_DISTRIBUTION
FI_SLOPE = 0.5
MINIMUM_DENSITY = 1080.  -3.
MAXIMUM_DENSITY = 2300 5.
```

5.1.2 The GRANULOMETRY block

This block of data (see Table 6) defines the variables needed by SETGRN . Commonly this block is appended to the HAZMAP 3.0 control input file. The meaning of each record is the following:

- `NUMBER_OF_CLASSES`: Number of granulometric classes.
- `DISTRIBUTION`: Type of distribution. It can be LINEAR or GAUSSIAN.
- `FI_MIN`: Minimum value of Φ.
- `FI_MAX`: Maximum value of Φ.
- `FI_MEAN`: Mean value of Φ. Only used if (DISTRIBUTION = GAUSSIAN).
- `FI_DISP`: Value of σ in the Gaussian distribution. Only used if (DISTRIBUTION = GAUSSIAN).
- `FI_SLOPE`: Slope of the linear distribution. Only used if (DISTRIBUTION = LINEAR).
- `MINIMUM_DENSITY`: Minimium value of density (in kg/m^3) and associated value of Φ. For values of Φ lower than this value (larger particles) density is assumed to be constant and equal to the minimum value.
- `MAXIMUM_DENSITY`: Maximum value of density (in kg/m^3) and associated value of Φ. For values of Φ larger than this value (smaller particles) density is assumed to be constant and equal to the maximum value.

5.2 The program SETSRC

The distribution of sources is defined in a source file (see section 3.2). The program SETSRC is an utility that reads the SOURCE block from the control input file and generates a source file. The source term is constant for a given time interval but there is no limit on the number and duration of the time intervals. It allows, in practise, to discretize any kind of time-dependency (time-dependent mass flow rate, column height, etc.). The program admits three possibilities: point source (mass is released in a single source point), Suzuki distribution (Suzuki , 1983; Pfeiffer et al., 2005), and buoyant plume model (Bursik , 2001). The last option is more elaborated and involves the solution of the 1D radial-averaged plume governing equations that describe the convective region of an eruptive column. These equations are intimately coupled with the wind field which, for small to medium size plumes, may induce a substantial plume bent-over and subsequent variations of plume height and mass release location. For this reason, when this option switched on, the program reads the values of the wind field from a meteorological file, computes the averaged wind direction and solves the plume governing equations for each time interval and particle class accounting for wind. Note that it introduces a time dependence in the source term even when all the eruptive parameters (mass flow rate, class fraction, etc.) are kept constant in time.

5.2.1 Program execution

To run SETSRC (see section 2.1 for installation details) simply type
"`SetSrc.exe FileLog FileInp FileSrc FileGrn FileMet MODEL MESH`" (on a Unix/Linux/Mac X OS)
or
"`SetSrc.win.exe FileLog FileInp FileSrc FileGrn FileMet MODEL MESH`" (on a Windows OS) where

- `FileLog`: Name (including path) of the SETSRC output log file.
- `FileInp`: Name (including path) of the control input file that contains the SOURCE block. Normally this file coincides with the HAZMAP 3.0 input file.
- `FileSrc`: Name (including path) of the source file. This is the output from SETSRC that is used later by HAZMAP 3.0 as input.
- `FileGrn`: Name (including path) of the granulometry file (normally generated previously by SETGRN).
- `FileMet`: Name (including path) of the meteo data file (see section 3.4).
- `MODEL`: Flag indicating the name of the model. For HAZMAP 3.0 it is always "HAZMAP".
- `MESH`: Flag that indicates if the discrete source points must be interpolated onto a mesh. For HAZMAP 3.0 it is always "NO".

Note that filenames are passed as a program call argument. It is highly recomended to launch SETSRC through the script files included in the distribution.

- On a Windows OS go to the folder `Hazmap-3.0/Utilities/SetSrc`, edit the script `Script-SetSrc-Windows` to change the "problemname" variable and launch the script.
- On a Mac X/Unix/Linux OS enter the folder `Hazmap-3.0/Utilities/SetSrc`, edit the script `Script-SetSrc-Unix` to change the "problemname" variable and launch the script.

5.2.2 The SOURCE block

This block of data (see Table 7) defines the variables needed by SETSRC . Commonly this block is appended to the HAZMAP 3.0 control input file. The meaning of each record is the following:

- `X_VENT_(UTM_M)`: x-coordinate of the vent (UTM coordinates in m).
- `Y_VENT_(UTM_M)`: y-coordinate of the vent (UTM coordinates in m).
- `MASS_FLOW_RATE_(KGS)`: Values of the mass flow rate (in kg/s). One value for each time interval. The duration of each time interval is constant and given by `RUN_START_(HOURS_AFTER_00)` minus `RUN_END_(HOURS_AFTER_00)` divided by the number of time intervals (automatically computed by the program from the number of values).
- `SOURCE_TYPE`: Type of source distribution. Possibilities are POINT, SUZUKI or PLUME.
- `HEIGHT_ABOVE_VENT_(M)`: Height of the source (in m above the vent). One value for each time interval.
- `A`: Parameter A in the Suzuki distribution. One value for each time interval. Used only if `SOURCE_TYPE = SUZUKI`.
- `L`: Parameter L in the Suzuki distribution. One value for each time interval. Used only if `SOURCE_TYPE = SUZUKI`.
- `EXIT_VELOCIY_(MS)`: Magma exit velocity (in m/s) at the vent. One value for each time interval. Used only if `SOURCE_TYPE = PLUME`.
- `EXIT_TEMPERATURE_(K)`: Magma exit temperature (in ^oK) at the vent. One value for each time interval. Used only if `SOURCE_TYPE = PLUME`.
- `EXIT_VOLATILE_FRACTION_(IN%)`: Magma volatile mass fraction at the vent. One value for each time interval. Used only if `SOURCE_TYPE = PLUME`.

Table 7: Sample of the SETSRC input file. Normally this block is appended at the end of the HAZMAP 3.0 input file. In this example a Suzuki source and two time intervals are assumed.

```
SOURCE
X_VENT_(UTM_M) = 500080.
Y_VENT_(UTM_M) = 4177690.
MASS_FLOW_RATE_(KGS) = 5d4 7d4          (One value for each source time interval)
SOURCE_TYPE = SUZUKI
POINT_SOURCE                            (Variables below are used only if SOURCE_TYPE = POINT)
HEIGHT_ABOVE_VENT_(M) = 2000.
SUZUKI_SOURCE                           (Variables below are used only if SOURCE_TYPE = SUZUKI)
HEIGHT_ABOVE_VENT_(M) = 3000.  3500.    (One value for each source time interval)
A = 4.  4.                              (One value for each source time interval)
L = 5.  5.                              (One value for each source time interval)
PLUME_SOURCE                            (Variables below are used only if SOURCE_TYPE = PLUME)
EXIT_VELOCIY_(MS) = 100.
EXIT_TEMPERATURE_(K) = 1073.
EXIT_VOLATILE_FRACTION_(IN%) = 0.
```

5.3 The program MODELPOSTP

The program MODELPOSTP (alias for Model Postprocess) is an optional utility that reads the output binary file of HAZMAP 3.0 , calculates some relevant quantities at selected time instants and produces elementary maps in GRD and PS formats.

5.3.1 Program execution

To run MODELPOSTP (see section 2.1 for installation details) simply type
"`ModelPostp.exe FileLog FileInp FileRes BASERES`" (on a Unix/Linux/Mac X OS) or
"`ModelPostp.win.exe FileLog FileInp FileRes BASERES`" (on a Windows OS) where

- `FileLog`: Name (including path) of the MODELPOSTP output log file.
- `FileInp`: Name (including path) of the control input file that contains the POSTPROCESS_MODELS block. Normally this file coincides with the HAZMAP 3.0 input file.
- `FileRes`: Name (including path) of the HAZMAP 3.0 results file. This is the output from HAZMAP 3.0 that is used by as input.
- `BASERES`: Path where the MODELPOSTP output files are dump.

Note that filenames are passed as a program call argument. It is highly recomended to launch MODELPOSTP through the script files included in the distribution.

- On a Windows OS go to the folder `Hazmap-3.0/Utilities/ModelPostp`, edit the script `Script-ModelPostp-Windows` to change the "problemname" variable and launch the script.
- On a Mac X/Unix/Linux OS enter the folder `Hazmap-3.0/Utilities/ModelPostp`, edit the script `Script-ModelPostp-Unix` to change the "problemname" variable and launch the script.

5.3.2 The POSTPROCESS_MODELS block

This block of data (see Table 8) defines the variables needed by MODELPOSTP . Commonly this block is appended to the HAZMAP 3.0 control input file. The meaning of each record is the following:

- `OUTPUT_FILES_IN_GRD_FORMAT`: Possibilities are YES or NO. If YES, MODELPOSTP plots files in GRD format. Files in GRD format can be readed directly by several plotting programs like the commercial software GRAPHER. Alternativelly, the user may also generate its own plots using functons from several free packages (*e.g.* gnuplot in FORTRAN).

Table 8: Sample of the ModelPostp input file. Normally this block is appended at the end of the Hazmap 3.0 input file.

```
POSTPROCESS_MODELS
OUTPUT_FILES_IN_GRD_FORMAT = YES
OUTPUT_FILES_IN_PS_FORMAT = NO
MAP_TOTAL_LOAD = YES
UNITS = KG/M2
CONTOUR_LEVELS = 0.1 0.25 0.5 1.  5.  10.  50.      (Only used if OUTPUT_FILES_IN_PS_FORMAT=YES)
MAP_CLASS_LOAD = NO
UNITS = KG/M2
CONTOUR_LEVELS = 0.1 0.25 0.5 1.  5.  10.  50.      (Only used if OUTPUT_FILES_IN_PS_FORMAT=YES)
MAP_DEPOSIT_THICKNESS = NO
UNITS = MM
COMPACTATION_FACTOR = 0.7
CONTOUR_LEVELS = 0.1 1.  5.  10.  50.  100.  500.   (Only used if OUTPUT_FILES_IN_PS_FORMAT=YES)
```

- `OUTPUT_FILES_IN_PS_FORMAT`: Possibilities are YES or NO. If YES, ModelPostp plots files in PS format.
- `MAP_TOTAL_LOAD`: Possibilities are YES or NO. If YES ModelPostp plots the total ground load.
- `UNITS`: Units of `MAP_TOTAL_LOAD`. It must be KG/M2.
- `CONTOUR_LEVELS`: Values of the contour levels for `MAP_TOTAL_LOAD`. Only used when `OUTPUT_FILES_IN_PS_FORMAT` is YES.
- `MAP_CLASS_LOAD`: Possibilities are YES or NO. If YES ModelPostp plots the class ground load.
- `UNITS`: Units of `MAP_CLASS_LOAD`. It must be KG/M2.
- `CONTOUR_LEVELS`: Values of the contour levels for `MAP_CLASS_LOAD`. Only used when `OUTPUT_FILES_IN_PS_FORMAT` is YES.
- `MAP_DEPOSIT_THICKNESS`: Possibilities are YES or NO. If YES ModelPostp plots total deposit thickness.
- `UNITS`: Units of `MAP_DEPOSIT_THICKNESS`. Possibilities are MM (for mm), CM (for cm), and M (for m).
- `COMPACTATION_FACTOR`: Deposit compactation factor.
- `CONTOUR_LEVELS`: Values of the contour levels for `MAP_DEPOSIT_THICKNESS`. Only used when `OUTPUT_FILES_IN_PS_FORMAT` is YES.

6 References

Arastoopour, H., Wang, C., Weil, S., 1982. Particle-particle interaction force in a dilute gassolid system. Chemical Engineering Science 37, 1379–1386.

Bursik, M., 2001. Effect of wind on the rise height of volcanic plumes. Geophys. Res. Lett. 18, 3621-3624.

Dellino, P., D. Mele, R. Bonasia, G. Braia, L. La Volpe, R. Sulpizio, 2005. The analysis of the influence of pumice shape on its terminal velocity, Geophys. Res. Lett., 32, L21306.

Ganser, G., 1993. A rational approachto drag prediction spherical and nonspherical particles. Powder Technology 77, 143–152.

Macedonio, G., Costa, A., Longo, A., 2005. A computer model for volcanic ash fallout and assessment of subsequent hazard. Computer and Geosciences 31, 837–845.

Pfeiffer, T., Costa, A., Macedonio, G., 2005. A model for the numerical simulation of tephra fall deposits. J. Volcanol. Geotherm. Res. 140, 273–294.

Wilson, L., and T. C. Huang, 1979. The influence of shape on the atmospheric settling velocity of volcanic ash particles, Earth Planet. Sci. Lett. 44, 311–324.

Suzuki, T., 1983. A theoretical model for dispersion of tephra. In: D. Shimozuru, I. Yokoyama (Eds.), Arc Volcanism: Physics and Tectonics, Terra Scientific Publishing Company (TERRAPUB), Tokyo.